

Microsoft Outlook 2003

1. Open Microsoft Outlook, click Tools > E-mail Accounts...



2. In the E-mail Accounts window, under E-mail, click Add a new e-mail account, and click Next.





3. For the **Server Type**, choose **POP3**, and click **Next**.

E-mail Accounts	
Server Type You can choose the type of server your new e-mail account will work with.	×
O <u>M</u> icrosoft Exchange Server	
Connect to an Exchange server to read e-mail, access public folders, and share documents.	
⊙ <u>P</u> OP3	
Connect to a POP3 e-mail server to download your e-mail.	
Connect to an IMAP e-mail server to download e-mail and synchronize mailbox folders.	
ОНТТР	
Connect to an HTTP e-mail server such as Hotmail to download e-mail and synchronize mailbox folders.	
O <u>A</u> dditional Server Types	
Connect to another workgroup or 3rd-party mail server.	
< <u>Back</u>	Cancel



4. Enter the following and click More Settings...

a.	Under User Information	Enter your full name and email address .
b.	Under Server Information	Enter your domain name with a " mail. " prefix (eg. <u>mail.yourdomain.com</u>) for both Incoming mail server (POP3) and Outgoing mail server (SMTP).

c. Under Logon Information Enter your email address and password.

E-mail Accounts					
Internet E-m Each of the	ail Settings (POP3) ese settings are required to g	et your e-mail account working.	×		
User Informat	ion	Server Information			
Your Name:	John Smith	Incoming mail server (POP3):	mail.yourdomain.com		
<u>E</u> -mail Address:	yourname@yourdomain.cc	Outgoing mail server (SMTP):	mail.yourdomain.com		
Logon Informa	ation	Test Settings			
User Name: yourname@yourdomain.cc		After filling out the information on this screen, we recommend you test your account by clicking the			
Password:	*****	button below. (Requires netwo	ork connection)		
Log on using Authenticatio	Secure Password	Test Account Settings	More Settings		
		< <u>B</u> ack	Next > Cancel		



5. Select the **Outgoing Server** tab.

iternet	E-mail Settings	j -		
General	Outgoing Server	Connection	Advanced	
Mail Acc Type accou	count the <u>n</u> ame by which unt. For example:	n you would lik "Work" or "Mic	e to refer to this crosoft Mail Server"	
mail.	yourdomain.com			
Other L	Jser Information		55 50	
<u>O</u> rgar	nization:			
<u>R</u> eply	E-mail:			
	ALC: NOT			
				_
		ſ	OK Cancel	



6. Enable **My outgoing server(SMTP) requires authentication**, choose **Log on Using** and enter **your email address** and **password**. Click **OK**.

Internet	E-mail Setting	i		×
General	Outgoing Server	Connection	Advanced	_
My My	outgoing server (SI	MTP) requires	authentication	
	lse same settings a	s my incoming	mail server	
	lser Name:	vourname®v	ourdomain.com	
E	eassword:	****		
		✓ <u>R</u> emember	password	
] [Log on using <u>S</u> ec	ure Password	Authentication (SPA)	i i
OL	og on to incoming n	nail server bef	ore sending mail	
1				
				ncel



7. Click Next.

E-mail Account	s		
Internet E-m Each of the	ail Settings (POP3) ese settings are required to g	et your e-mail account working.	×
User Informat	tion	Server Information	
Your Name:	John Smith	Incoming mail server (POP3):	mail.yourdomain.com
<u>E</u> -mail Address:	yourname@yourdomain.cc	Outgoing mail server (SMTP):	mail.yourdomain.com
Logon Information User Name: yourname@yourdomain.cc		Test Settings	
		After filling out the information recommend you test your acco	on this screen, we bunt by clicking the
Password:	Remember password	Test Account Settings	ork connection)
Log on using Secure Password Authentication (SPA)		<u> </u>	More Settings
		< <u>B</u> ack	Next > Cancel



8. Click Finish.

